

I/O of sound with R

Jérôme Sueur *

March 26, 2009

This document shortly details how to import and export sound with R using the packages `seewave`, `sound`, `tuneR` and `audio`.

Contents

1	In	2
1.1	Non specific classes	2
1.1.1	Vector	2
1.1.2	Matrix	2
1.2	Time series	3
1.3	Specific sound classes	3
1.3.1	Wave class (package <code>tuneR</code>)	3
1.3.2	Sample class (package <code>sound</code>)	4
1.3.3	audioSample class (package <code>audio</code>)	5
2	Out	6
2.1	.txt format	6
2.2	.wav format	6
2.3	.flac format	6
3	Mono and stereo	6
3.1	Wave class	7
3.2	Sample class	7
4	Play sound	8
4.1	Specific functions	8
4.1.1	Wave class	8
4.1.2	Sample class	8
4.1.3	audioSample class	9
4.1.4	Other classes	9
4.2	System command	9
5	Summary	9

*Muséum national d'Histoire naturelle, Paris, France – <http://sueur.jerome.perso.neuf.fr>

1 In

The main functions of **seewave** (>1.5.0) can use different classes of objects to analyse sound: (i) usual classes (numeric **vector**, numeric **matrix**), (ii) time series classes (**ts**, **mts**), and (iii) sound-specific classes (**Wave**, **Sample**, **audioSample**).

1.1 Non specific classes

1.1.1 Vector

Any numeric vector can be treated as a sound if a sampling frequency is provided in the **f** argument of **seewave** functions. For instance, a 440 Hz sine sound (A note) sampled at 8000 Hz during one second can be generated and plot following:

```
> s1 <- sin(2 * pi * 440 * seq(0, 1, length.out = 8000))
> is.vector(s1)

[1] TRUE

> mode(s1)

[1] "numeric"

> library(seewave)

Welcome to seewave!
The package is regularly updated, check for new version
Please see citation('seewave') if you use 'seewave' in publications

> oscillo(s1, f = 8000)
```

1.1.2 Matrix

Any single column matrix can be read but the sampling frequency has to be specified in the **seewave** functions.

```
> s2 <- as.matrix(s1)
> is.matrix(s2)

[1] TRUE

> dim(s2)

[1] 8000    1

> oscillo(s2, f = 8000)
```

If the matrix has more than one column, then the first column only will be considered.

```
> x <- rnorm(8000)
> s3 <- cbind(s2, x)
> is.matrix(s3)

[1] TRUE

> dim(s3)

[1] 8000    2

> oscillo(s3, f = 8000)
```

1.2 Time series

The class `ts` and the related functions `ts`, `as.ts`, `is.ts` can be used also for sound. Here follows the command to similarly generate a time series corresponding to a 440 Hz sine sound sampled at 8000 Hz during one second:

```
> s4 <- ts(data = s1, start = 0, frequency = 8000)
> str(s4)

Time-Series [1:8000] from 0 to 1: 0 0.339 0.637 0.861 0.982 ...
```

To generate a 0.5 second random noise:

```
> s4 <- ts(data = runif(4000), start = 0, end = 0.5, frequency = 8000)
> str(s4)

Time-Series [1:4001] from 0 to 0.5: 0.4518 0.4625 0.8146 0.0373 0.1307 ...
```

The length of `s4` is not 4000 but 4001. Data are actually recycled, `s4[4001]` being the same as `s4[1]`. The functions `frequency` and or `deltat` return the sampling frequency (f) and the time resolution (Δt) respectively:

```
> frequency(s4)

[1] 8000

> deltat(s4)

[1] 0.000125
```

As the frequency is embedded in `ts` objects, there is no need to specify it when using `seewave` functions:

```
> oscillo(s4)
```

In the case of multiple time series, `seewave` functions will consider the first series only:

```
> s5 <- ts(data = s3, f = 8000)
> class(s5)

[1] "mts" "ts"

> oscillo(s5)
```

1.3 Specific sound classes

There are two object classes corresponding to the binary `wav` format: (i) the class `Wave` of the package `tuneR`, (ii) the class `Sample` of the package `sound`. There is currently no other way to import sound files. In particular, there is no function to read `.mp3` or `.aiff` files.

1.3.1 Wave class (package `tuneR`)

The class `Wave` comes with the package `tuneR` managed by Uwe Ligges. This S4 class includes different slots with the data (left or right channel), the sampling frequency (or rate), the number of bits (8 /16 /24 /32) and the type of sound (mono /stereo). High sampled sound (*i.e.* > 44100 Hz) can be read. The function to import `.wav` files from the hard-disk is `readWave`:

```
> library(tuneR)
> s6 <- readWave("mysong.wav")
> s6
```

Wave Object

```
Number of Samples:    480000
Duration (seconds):   60
Samplingrate (Hertz): 8000
Channels (Mono/Stereo): Mono
Bit (8/16/24/32):    16
```

The other advantage of using `readWave` is for reading part of long files. It is indeed possible to import only a section of the `.wav` file using the arguments `from` and `to` and by specifying the time units with the arguments `units`. The units can be turned to "samples", "minutes" or "hours". For instance, to read only the section starting at 1s and ending at 5s of the file "mysong.wav" :

```
> s7 <- readWave("mysong.wav", from = 1, to = 5, units = "seconds")
> s7
```

Wave Object

```
Number of Samples:    32000
Duration (seconds):   4
Samplingrate (Hertz): 8000
Channels (Mono/Stereo): Mono
Bit (8/16/24/32):    16
```

To get information regarding the object (sampling frequency, number of bits, mono /stereo), it is necessary to use the indexing of S4 object classes:

```
> s7@samp.rate
[1] 8000

> s7@bit
[1] 16

> s7@stereo
[1] FALSE
```

1.3.2 Sample class (package sound)

The class `Sample` and the related `as.Sample` and `is.Sample` functions belong to the package `soundwritten` by Matthias Heymann. Like `Wave`, the `Sample` class is a list containing information regarding data, sampling frequency, bits and the type of sound (mono/stereo).

To read a `.wav` file stored on the hard-disk using `loadSample`:

```
> s8 <- loadSample("mysong.wav")
> s8

type      : mono
rate      : 8000 samples / second
quality   : 16 bits / sample
length    : 480000 samples
R memory  : 1920000 bytes
HD memory : 960044 bytes
duration  : 60 seconds
```

All kinds of wav files are supported: mono, stereo, 8 or 16 bits per sample, at any sampling frequency above 1000 Hz. The duration and the sampling frequency of a `Sample` object can be obtained using dedicated functions or list indexing:

```
> rate(s8)
```

```
[1] 8000

> s8$rate

[1] 8000

> duration(s8)

[1] 60

> s8$duration

NULL
```

seewave functions which return a value describing a sound have a special argument named **Sample**. When this argument is set to **TRUE**, the object returned by the function is of class **Sample** and not **matrix**. This can be useful for latter analyses as there is no more need to specify the sampling frequency **f**.

```
> s9 <- repw(s2, f = 8000, times = 2, Sample = TRUE)
> oscillo(s9)
```

However, matrix objects are easier to handle and can be used with functions not dedicated to sound. It might be then better to let the argument **Sample** set to **FALSE** and to store the sampling frequency **f** in an object:

```
> f <- 8000
> oscillo(s2, f)
```

1.3.3 audioSample class (package audio)

The package **audio**, developed by Simon Urbanek, is another option to handle **.wav** files. Sound can be imported using the function **load.wave**. The class of the resulting object is **audioSample** which is essentially a numeric vector (for mono) or numeric matrix with two rows (for stereo). The sampling frequency and the resolution can be called as attributes :

```
> library(audio)
> s10 <- load.wave("mysong.wav")
> head(s10)

sample rate: 8000Hz, mono, 16-bits
[1] 0.0000000 0.4713745 0.6666260 0.4713745 0.0000000 -0.4713889

> s10$rate

[1] 8000

> s10$bits

[1] 16
```

The main advantage of the package **audio** is that sound can be directly acquired within an R session. This is achieved by first preparing a vector of **NA** and then using the function **record**. For instance, to get a mono sound of 5 seconds sampled at 16 kHz :

```
> s11 <- rep(NA_real_, 16000 * 5)
> record(s11, 16000, 1)
```

A recording session can be controlled using three complementary functions : **pause**, **rewind**, and **resume** (see 4.1.3). See the documentation of **audio** for details regarding the control of audio drivers: <http://www.rforge.net/audio/>.

2 Out

2.1 .txt format

For a maximal compatibility with other sound softwares, it can be useful to save a sound as a simple `.txt` file. This can be done using the function `export` with the argument `header=FALSE`. By default, the name of the object is used to name the `.txt` file. The following commands will write a file "tico.txt" on the hard-disk.

```
> data(tico)
> export(tico, f = 22050, header = FALSE)
```

For Windows users, the software [Goldwave ©](#) can be helpful when handling long sound files or large number of files. To export a sound as a `.txt` file that can be directly read by [Goldwave ©](#), the same function can be used but with the default argument `header=TRUE`. `seewave` will automatically add the header needed. Hereafter the name of the exported file is changed using the argument `filename`:

```
> export(tico, f = 22050, filename = "tico_Gold.txt")
```

Any header can be specified for a connection with other softwares. For instance, if an external software needs the header "f=sampling frequency; ch=left":

```
> export(tico, f = 22050, filename = "tico_ext.txt", header = "f=22050; ch=left")
```

2.2 .wav format

`tuneR`, `soundand` and `audiohave` each function to write `.wav` files: `writeWave`, `saveSample`, and `save.wave` respectively. Within `seewave` the function `savewav`, which is based on `saveSample`, can be used to save data as `.wav`. By default, the name of the object will be used for the name of the `.wav` file:

```
> savewav(tico, f = 22050)
```

As seen before, if the object to be saved is of class `ts`, `Sample` or `Wave`, there is no need to specify the argument `f`. Here we use the argument `filename` to change the name of the `wav` file:

```
> ticofirst <- cutw(tico, f = 22050, to = 0.5, Sample = TRUE)
> savewav(ticofirst, filename = "tico_firstnote.wav")
```

2.3 .flac format

Free Lossless Audio Codec (FLAC) is a file format by Josh Coalson for lossless audio data compression. FLAC reduces bandwidth and storage requirements without sacrificing the integrity of the audio source. Audio sources encoded to FLAC are typically reduced in size 40 to 50 percent. See the [flac webpage](#) for details.

`.flac` format cannot be used as such with R. However, the function `wav2flac` allows to call FLAC software directly from the console. FLAC has therefore to be installed on your OS. If you have a `.wav` file you wish to compress into `.flac`, call:

```
> wav2flac("tico_firstnote.wav", overwrite=TRUE)
```

To compress a `.wav` file into `.flac`, the argument `reverse` has to be set to `TRUE`:

```
> wav2flac("tico_firstnote.flac", reverse=TRUE)
```

3 Mono and stereo

Both `Wave` and `Sample` classes can handle stereo files. There are some specific functions regarding mono/stereo type. Both libraries include functions with the same name. To avoid a conflict between functions, one of the two has to be detached:

```
> detach(package:sound)
```

3.1 Wave class

To generate a stereo sound, two mono sounds are first created using `sine`, a function that returns a `Wave` object, and then combined using `stereo`:

```
> left <- sine(440, bit = 16)
> right <- sine(2000, bit = 16)
> s12 <- stereo(left, right)
> s12
```

Wave Object

```
Number of Samples:    44100
Duration (seconds):    1
Samplingrate (Hertz): 44100
Channels (Mono/Stereo): Stereo
Bit (8/16/24/32):     16
```

To go back to a mono file taking the left channel only:

```
> s13 <- mono(s12, "left")
```

The function `channel` do roughly the same as it extracts one or more channels. To get this time the right channel:

```
> s14 <- channel(s12, "right")
```

And eventually, the S4 indexing can be used to do it "manually". In this particular case, the returned object will be of class `vector`.

```
> s13 <- s12@left
> is.vector(s13)
```

```
[1] TRUE
```

```
> s14 <- s12@right
> is.vector(s14)
```

```
[1] TRUE
```

3.2 Sample class

With the `Sample` objects, the syntax is almost similar. To generate stereo sound, the function `synth` with the argument `Sample=TRUE` is called twice:

```
> left <- synth(cf = 440, d = 5, f = 8000, Sample = T)
> right <- synth(cf = 2000, d = 5, f = 8000, Sample = T)
> s13 <- stereo(left, right)
> s13
```

```
type      : stereo
rate      : 8000 samples / second
quality   : 16 bits / sample
length    : 40000 samples
R memory  : 320000 bytes
HD memory : 160044 bytes
duration  : 5 seconds
```

To get either the left or right channel:

```
> s14 <- left(s13)
> s14
```

```

type      : mono
rate      : 8000 samples / second
quality   : 16 bits / sample
length    : 40000 samples
R memory  : 160000 bytes
HD memory : 80044 bytes
duration  : 5 seconds

```

```

> s15 <- right(s13)
> s15

```

```

type      : mono
rate      : 8000 samples / second
quality   : 16 bits / sample
length    : 40000 samples
R memory  : 160000 bytes
HD memory : 80044 bytes
duration  : 5 seconds

```

List indexing allows extracting manually the data:

```

> s16 <- s13$sound[1, ]
> is.vector(s16)

```

```
[1] TRUE
```

```

> s17 <- s13$sound[2, ]
> is.vector(s17)

```

```
[1] TRUE
```

The `mirror` function interchanges left and right channels and `panorama` control the panorama through a `pan` argument which varies between -50 and +50.

```

> s13 <- mirror(s13)
> s14 <- panorama(s13, pan = 30)

```

4 Play sound

4.1 Specific functions

4.1.1 Wave class

Wave objects can be played with `play` of `tuneR`:

```
> play(s6)
```

It may happen that the default players of the function `play` are not installed on the OS. Three functions can help in setting the media player: `findWavPlayer` returns the most common system commands on the OS, `WavPlayer` returns the command that is currently used by `play`, `setWavPlayer` is used to define the command to be used by `play`. For instance, if [Audacious](#) is the player to use (Linux OS):

```
> setWavPlayer("audacious")
```

4.1.2 Sample class

For the class `Sample` of the package `tuneR` the functions are basically the same. The function `play`:

```

> play(ticofirst)
> play("mysong.wav")

```

and the functions `WavPlayer`, `setWavPlayer`, `getWavPlayer` to set the sound player of your OS.

4.1.3 audioSample class

The package `audio` has similarly a function `play` but also have three useful functions to control recording and playback :

- `pause` that stops audio recording or playback,
- `rewind` that rewinds audio recording or playback, *i.e.*, makes the beginning of the source (or target) object the current audio position,
- `resume` that resumes previously paused audio recording or playback.

4.1.4 Other classes

The package `seewave` includes `listen` a function based on `play` of `soundR` but accepting all specific and non-specific classes and with two arguments (`from` and `to`) to listen only a section of a sound object:

```
> listen(s1, f=8000, from=0.3, to=7)
> listen(s13, from=0.3, to=4)
```

4.2 System command

The call of an external sound player can also be achieved using directly `system` that allows invoking directly the system command. For instance, to play a sound with [Audacity](#) (Linux OS):

```
> system("audacity mysong.wav")
```

To run a sound player with Windows is slightly more tricky as the complete path to the .exe file has to be specified and `paste` has to be invoked to combine both program and file names:

```
> system(paste('"C:/Program Files/GoldWave/GoldWave.exe"', 'mysong.wav'))
```

5 Summary

Here is a tentative of summary of main R functions used for sound input and output:

	Input	Output	Mono/Stereo	Play	Object
tuneR	<code>readWave</code>	<code>writeWave</code>	mono, stereo	<code>play</code>	<code>Wave</code>
sound	<code>loadSample</code>	<code>saveSample</code>	mono, stereo	<code>play</code>	<code>Sample</code>
audio	<code>load.wave</code> , <code>record</code>	<code>save.wave</code>	mono, stereo	<code>play</code> , <code>pause</code> , <code>resume</code> , <code>rewind</code>	<code>audioSample</code>
seewave	–	<code>export</code> , <code>savewav</code>	–	<code>listen</code>	<code>vector</code> , <code>matrix</code> , <code>ts</code> , <code>mts</code> , <code>Wave</code> , <code>Sample</code> , <code>audioSam-</code> <code>ple</code>